


Business Broadband Service IPv6 Configuration Guide [Windows 7 / Vista]


(Version 2.0)

Windows Vista / Windows 7

- 1. From the task bar, click Start and select Control Panel
- 2. Click Network & Internet, and then choose Network Connections
- 3. Double Click the connection that you want to change




4. Click Properties




Version 2.0 2

- 5. Select Networking tab page and then select Internet Protocol Version 6 (TCP/IPv6)
- 6. Click Properties



7. Click Properties


For Auto IP address assignment, please click the following two fields:



Version 2.0

For hard code the IP address, select Use the following IPv6 Address:

- Type in "IPv6 address", "Subnet Prefix Length" and "Default Gateway address" as the following screen.
- Type in "Preferred DNS server". Then click **OK** to finish the set up.



8. Test the connection, open the Internet Explorer, type the website which has IPv6 address, e.g. www.gov.hk



Version 2.0 4

- 9. Check the connection and the IPv6 address: Open the command prompt Type "nslookup [website]"
 - e.g., nslookup www.gov.hk and you can find the www.gov.hk IPv6 address

```
Pinging 2407:8000:8002:1ff::1 from 2407:8000:8002:1ff::2 with 32 bytes of data:
Reply from 2407:8000:8002:1ff::1: time-1ms
Reply from 2407:8000:8002:1ff::1: time/1ms
Reply from 2407:8000:8002:1ff::1: time/1ms
Reply from 2407:8000:8002:1ff::1: time/1ms
Reply from 2407:8000:8002:1ff::1: time/1ms
Ping statistics for 2407:8000:8002:1ff::1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\Users\Jack\nslookup www.gov.hk
Server: UnKnown
Address: 2002:d596:2a92:1:71:53::
Non-authoritative answer:
Name: www.gov.hk
Addresses: 2406:0:6a:8001::212
    202.128.243.212
    202.128.243.212
    202.128.238.167
```

10. Type "netstat". Will see the IPv6 address for www.gov.hk.

```
Administrator: Command Prompt
'nestat' is not recognized as an internal or external command, operable program or batch file.
C:\Users\Jack>netstat
Active Connections
                                   Foreign Address
PoleCat:1030
PoleCat:1029
          Local Address
  Proto
         127.0.0.1:1029
127.0.0.1:1030
                                                             ESTABLISHED
  TCP
                                                             ESTABLISHED
            7.0.0.1:1032
                                    PoleCat:1033
                                   PoleCat:1032
                                   Po leCat : 5939
Po leCat : 27015
              0.0.1:1035
0.0.1:1054
                                    PoleCat:1035
                                                              ESTABLISHED
                                    PoleCat:1054
                                                              ESTABLISHED
                                    PoleCat:14147
                                                              ESTABLISHED
                                    PoleCat:57903
                                    PoleCat:5
                                    PoleCat:5
                                                             ESTABLISHED
            C:\Users\Jack>
```

Version 2.0 5